


Using the S2-LP GUI

AMG RF Application team



What do we need?





Open the COM port 3


- If the STM32 NUCLEO PC driver is correctly installed on the PC, the board will be enumerated.
- The COM port assigned to the board will be shown on the COM port combo box.
- Clicking on open, the GUI will do some preliminary checks:
 - 1. ask the firmware version
 - 2. Compare with the minimal version required
 - 3. If it does not respond to the version it will ask the user to proceed with an automatic FW update









Functionalities of the S2-LP GUI





Radio setting 5






Firmware Upgrade...

Flash the firmware on the motherboard. This function makes use of the embedded ST-Link of the Nucleo board.

Firmware Version

Read the firmware version.



Export code configuration...

This option generates a C-language list of instructions that write on the S2-LP registers the values that are different from the default values to quickly configure the device.


Export production info...

Saves a text file containing the manufacturing info of the board.



Emulator ____

- The GUI can simulate the presence of a device thanks to an emulator.
 - the user should specify manually a XTAL frequency.
 - From there on, clicking the button "Open" everything related to the device configuration should run exactly as if a device is connected.



The intent is to allow the user to select his own configuration easily and then see or save the register values that are needed in order to keep the same configuration on his firmware. For this purpose, this feature can be used in cooperation with the "Export code configuration" tool.




Table of registers **8**


- It is possible to change the registers setting by clicking on a specific register (Value column) and writing the new value. When a register has changed, its value is highlighted in red.It is not possible to write the reserved fields
- Double clicking on a register, a detailed description of its fields is provided.
- The GUI can Export the the current register configuration. This will save all the registers to a .xml file.
- A configuration that has been exported can be imported using the Import button.

Transmission Test - TX

The TX tab allows to start the transmission routine.

- **Total Packets:** number of packets to be transmitted.
- **Ref timer:** the time period for the S2-LP to start a transmission slot.
- Payload length: length of the message. It is automatically updated when writing the message content on the payload line text
- Clicking on **START**, the transmission routine will be started:
 - the node will transmit a packet.
 - after the first packet is transmitted, it will go in IDLE state according to the figure below.
 - After the Ref timer has elapsed, another packets is TX.







Transmission Test - RX 10

The RX tab allows to start the reception routine.


- Total Packets: number of packets to be received.
- **Ref timer:** the time period for the S2-LP to open the RX slot.
- **RX timeout:** duration of the RX slot.
- Clicking on **START**, the reception routine will be started:
 - the node will go in RX with infinite timeout.
 - after the first packet is received, it will go in RX according to the figure below.
 - If the TX has the same Ref timer and the RX timeout is greater than the SYNC and preamble duration, each packet will be received.





Transmission Test - RX

- During the un-active phase of the reference time, the device will go:
 - in READY, if the Low Power check is unset
 - in STANDBY, if the Low Power check is set




Special cases are:

- Reference time = 0 and RX timeout=0, in this case, the device will be set always in RX (so no slots, no READY nor STDBY states).
- Packets number = $0 \rightarrow$ receive infinite packets. The reception routine won't be aborted until the *STOP* button is pressed.




Transmission Test – TX and RX

- The RX must be started first.
- When the first TX packet is received, the RX will start its cycles of Ref Time (un-active phase as desc. before) and RX (RX state).






Transmission Test - RX



- **Sense RSSI** button: used to sense the RSSI on the channel (that is set through the radio configuration part). If no signal is present, this gives an indication on the noise floor.
- **RSSI threshold** *spin box:* sets the minimum RSSI threshold that the message should have. This is used to increase the performance of the receiver and avoid that noise can disturb the reception.
- Sniff mode check box: this allows to switch the reception mode in sniff mode (also called *fast rx termination*).



Transmission Test – RX Sniff mode




The receiver wakes up periodically and sniffs the channel.

- If RSSI is detected above the RSSI threshold, the receiver stays in RX and searches the SYNC word
 - If SYNC is detected, the packet is received
 - Else, the **RX timeout** elapses and the device is set to SLEEP again
- Otherwise it goes back to SLEEP




To ensure a correct reception, the preamble duration of the <u>transmitted</u> packet (TX side) should be bigger than the wake up time of the receiver

Low Level Command TAB 15



Read/Write registers dialog 16

- It is a test mode tab that allows to:
 - Read registers
 - Write registers (without constraints of reserved fields)
 - Send command strobes to the device






Measuring the TX power 17

- Connect the board to a spectrum analyzer centered to the base frequency selected in the **GUI**
 - Click on TX CW START to generate a tone (unmodulated carrier)



 Click on TX PN9 START to generate a PN9 modulated signal according to the parameters specified in the radio configuration section







Sensitivity test with the GUI 18

To run a sensitivity test with the GUI it is possible to use the "BER" option" that many signal generators have (ex. Agilent e4438C).

For the low level command TAB click on the Send data on GPIO No. packet and connect the instrument as follows:

